

> User object

The following objects are directly related to the user API.

User

The user object has the following properties.

Property	Type	Description
userid	string	<i>(readonly)</i> ID of the user.
alias <i>(required)</i>	string	User alias.
attempt_clock	timestamp	<i>(readonly)</i> Time of the last unsuccessful login attempt.
attempt_failed	integer	<i>(readonly)</i> Recent failed login attempt count.
attempt_ip	string	<i>(readonly)</i> IP address from where the last unsuccessful login attempt came from.
autologin	integer	Whether to enable auto-login. Possible values: 0 - <i>(default)</i> auto-login disabled; 1 - auto-login enabled.
autologout	string	User session life time. Accepts seconds and time unit with suffix. If set to 0s, the session will never expire. Default: 15m.
lang	string	Language code of the user's language, for example, en_GB. Default: default - system default.
name	string	Name of the user.
refresh	string	Automatic refresh period. Accepts seconds and time unit with suffix. Default: 30s.
rows_per_page	integer	Amount of object rows to show per page. Default: 50.
surname	string	Surname of the user.
theme	string	User's theme. Possible values: default - <i>(default)</i> system default; blue-theme - Blue; dark-theme - Dark.
type	integer	Type of the user. Possible values: 1 - <i>(default)</i> Zabbix user; 2 - Zabbix admin; 3 - Zabbix super admin.
url	string	URL of the page to redirect the user to after logging in.

Property	Type	Description
timezone	string	User's time zone, for example, Europe/London, UTC. Default: default - system default. For the full list of supported time zones please refer to PHP documentation .

Media

The media object has the following properties.

Property	Type	Description
mediatypeid (required)	string	ID of the media type used by the media.
sendto (required)	string/array	Address, user name or other identifier of the recipient. If type of Media type is e-mail, values are represented as array. For other types of Media types , value is represented as a string.
active	integer	Whether the media is enabled. Possible values: 0 - (default) enabled; 1 - disabled.
severity	integer	Trigger severities to send notifications about. Severities are stored in binary form with each bit representing the corresponding severity. For example, 12 equals 1100 in binary and means, that notifications will be sent from triggers with severities warning and average. Refer to the trigger object page for a list of supported trigger severities. Default: 63
period	string	Time when the notifications can be sent as a time period or user macros separated by a semicolon. Default: 1-7,00:00-24:00

From: <https://www.zabbix.com/documentation/5.2/> - **Zabbix Documentation 5.2**

Permanent link: <https://www.zabbix.com/documentation/5.2/manual/api/reference/user/object>

Last update: **2020/08/06 11:59**

