

1 Configuring a host

Overview

To configure a host in Zabbix frontend, do the following:

- Go to: *Configuration* → *Hosts*
- Click on *Create* to the right (or on the host name to edit an existing host)
- Enter parameters of the host in the form

You can also use the *Clone* and *Full clone* buttons in the form of an existing host to create a new host. Clicking on *Clone* will retain all host parameters and template linkage (keeping all entities from those templates). *Full clone* will additionally retain directly attached entities (applications, items, triggers, graphs and low-level discovery rules).

Note: When a new host is cloned, it will retain all template entities as they are originally on the template. Any changes to those entities made on the existing host level (such as changed item interval, modified regular expression or added prototypes to the low-level discovery rule) will not be cloned to the new host; instead they will be as on the template.

Configuration

The **Host** tab contains general host attributes:

The screenshot shows the Zabbix Host configuration form. At the top, there are tabs for Host, Templates, IPMI, Macros, and Host inventory. The Host tab is active. The form contains the following fields and sections:

- Host name:** Zabbix server
- Visible name:** (empty)
- Groups:** In groups: Zabbix servers; Other groups: Discovered hosts, Linux servers, Templates
- New host group:** (empty)
- Agent interfaces:** IP address: 192.168.3.2, DNS name: (empty), Connect to: IP, DNS; Port: 10050, Default: (checked), Remove: (button)
- SNMP interfaces:** Add (button)
- JMX interfaces:** Add (button)
- IPMI interfaces:** Add (button)
- Monitored by proxy:** (no proxy) (dropdown)
- Status:** Monitored (dropdown)

At the bottom of the form, there are buttons for Save, Clone, Full clone, Delete, and Cancel.

Parameter	Description
<i>Host name</i>	Enter a unique host name. Alphanumerics, spaces, dots, dashes and underscores are allowed. <i>Note:</i> With Zabbix agent running on the host you are configuring, the agent configuration file parameter <i>Hostname</i> must have the same value as the host name entered here. The name in the parameter is needed in the processing of active checks .
<i>Visible name</i>	If you set this name, it will be the one visible in lists, maps, etc. This attribute has UTF-8 support.
<i>Groups</i>	Select host groups the host belongs to. A host must belong to at least one host group.
<i>New host group</i>	A new group can be created and linked to the host. Ignored, if empty.
<i>Interfaces</i>	Several host interface types are supported for a host: <i>Agent</i> , <i>SNMP</i> , <i>JMX</i> and <i>IPMI</i> . To add a new interface, click on <i>Add</i> in the <i>Interfaces</i> block and enter <i>IP/DNS</i> , <i>Connect to</i> and <i>Port</i> info. <i>Note:</i> Interfaces that are used in any items cannot be removed and link <i>Remove</i> is greyed out for them.
<i>IP address</i>	Host IP address (optional).
<i>DNS name</i>	Host DNS name (optional).
<i>Connect to</i>	Clicking the respective button will tell Zabbix server what to use to retrieve data from agents: IP - Connect to the host IP address (recommended) DNS - Connect to the host DNS name
<i>Port</i>	TCP/UDP port number. Default values are: 10050 for Zabbix agent, 161 for SNMP agent, 12345 for JMX and 623 for IPMI.
<i>Default</i>	Check the radio button to set the default interface.
<i>Monitored by proxy</i>	The host can be monitored either by Zabbix server or one of Zabbix proxies: (no proxy) - host is monitored by Zabbix server Proxy name - host is monitored by Zabbix proxy "Proxy name"
<i>Status</i>	Host status: Monitored - Host is active, ready to be monitored Not monitored - Host is not active, thus not monitored

The **Templates** tab allows you to link [templates](#) to the host. All entities (items, triggers, graphs and applications) will be inherited from the template.

To link a new template, click on *Add*. To unlink a template, use one of the two options:

- *Unlink* - unlink the template, but preserve its items, triggers and graphs
- *Unlink and clear* - unlink the template and remove all its items, triggers and graphs

The **IPMI** tab contains IPMI management attributes.

Parameter	Description
<i>Authentication algorithm</i>	Select the authentication algorithm.
<i>Privilege level</i>	Select the privilege level.
<i>Username</i>	User name for authentication.
<i>Password</i>	Password for authentication.

The **Macros** tab allows you to define host-level [user macros](#).


The **Host inventory** tab allows you to manually enter [inventory](#) information for the host. You can

also select to enable *Automatic* inventory population, or disable inventory population for this host.

Configuring a host group

To configure a host group in Zabbix frontend, do the following:

- Go to: *Configuration* → *Host groups*
- Click on *Create Group* in the upper right corner of the screen
- Enter parameters of the group in the form



Parameter	Description
<i>Group name</i>	Enter a unique host group name. The name must be unique within a Zabbix node.
<i>Hosts</i>	Select hosts, members of the group. A host group may have zero, one or more hosts.

From:

<https://www.zabbix.com/documentation/2.0/> - **Zabbix Documentation 2.0**

Permanent link:

<https://www.zabbix.com/documentation/2.0/manual/config/hosts/host>

Last update: **2015/11/26 09:19**

